

**NAME**

**kbdcontrol** - keyboard control and configuration utility

**SYNOPSIS**

```
kbdcontrol [-dFKix] [-A name] [-a name] [-b duration.pitch | belltype] [-r delay.repeat | speed]  
[-I keymap_file] [-f # string] [-k keyboard_device] [-L keymap_file] [-P path]
```

**DESCRIPTION**

The **kbdcontrol** command is used to set various keyboard related options for the syscons(4) or vt(4) console driver and the keyboard drivers, such as key map, keyboard repeat and delay rates, bell characteristics etc.

Keyboard options may be automatically configured at system boot time by setting variables in */etc/rc.conf*. See *Boot Time Configuration* below.

The following command line options are supported:

**-A *name***

Detach the keyboard, specified by the keyboard device name, from the keyboard multiplexer. When using this option, the standard input of the **kbdcontrol** process should be redirected from the keyboard multiplexer keyboard device (if the keyboard multiplexer is not the active keyboard) or */dev/console* (if the keyboard multiplexer is the active keyboard and you are not working on the system console).

**-a *name***

Attach the keyboard, specified by the keyboard device name, to the keyboard multiplexer. When using this option, the standard input of the **kbdcontrol** process should be redirected from the keyboard multiplexer keyboard device (if the keyboard multiplexer is not the active keyboard) or */dev/console* (if the keyboard multiplexer is the active keyboard and you are not working on the system console).

**-b *duration.pitch* | *belltype***

Set the bell duration in milliseconds and pitch in hertz. If a *belltype* argument is specified, it may be one of **normal** which sets sound parameters back to normal values, **off** which disables the bell entirely, or **visual** which sets the bell to visual mode, i.e., flashes the screen instead. If *belltype* is preceded by the word **quiet.**, the bell will not be rung when the ringing process is in the background vty. The **visual** bell, when chosen, applies to all vtys; other bell types can be set individually for each vty.

**-r *delay.repeat* | *speed***

Set keyboard *delay* (250, 500, 750, 1000) and *repeat* (34, 38, 42, 46, 50, 55, 59, 63, 68, 76, 84, 92, 100, 110, 118, 126, 136, 152, 168, 184, 200, 220, 236, 252, 272, 304, 336, 368, 400, 440, 472, 504) rates, or if a *speed* argument is specified, it may be one of **slow** (1000.504), **fast** (250.34) or **normal** (500.126).

**-I** *keymap\_file*

Install keyboard map file from *keymap\_file*. You may load the keyboard map file from a menu-driven command, `kbdmap(1)`. The format of keyboard map files is documented in the `kbdmap(5)` manual page.

**-d** Dump the current keyboard map onto stdout. The output may be redirected to a file and can be loaded back to the kernel later by the **-I** option above.

**-f** # *string*

Set function key number # to send *string*. Refer to the man page for the keyboard driver (e.g. `atkbd(4)`) for available function keys and their numbers.

**-F** Set function keys back to the standard definitions.

**-x** Use hexadecimal numbers in keyboard map dump.

**-i** Print brief information about the keyboard.

**-K** Disconnect the keyboard from the console. You need to use the **-k** option below to associate a keyboard with the console again.

**-k** *keyboard\_device*

Use the specified device as the console keyboard. When using this option, the standard input of the `kbdcontrol` process should be redirected from `/dev/console` if you are not working on the system console (see the *EXAMPLES* section).

**-L** *keymap\_file*

Load keyboard map file from *keymap\_file* and write the *struct keymap* compiled from it to stdout. This option is primarily intended for programmers and is probably of little use under normal circumstances.

**-P** *path*

Search for the keymap file in *path*. The **-P** option may be specified multiple times.

## ENVIRONMENT

The environment variable `KEYMAP_PATH` can hold an alternative path to the keyboard map files.

## KEYBOARD CONFIGURATION

### Boot Time Configuration

You may set variables in `/etc/rc.conf` or `/etc/rc.conf.local` in order to configure the keyboard at boot time. The following is the list of relevant variables.

*keymap* Specifies a keyboard map file for the **-l** option.  
*keyrate* Sets the keyboard repeat rate for the **-r** option.  
*keychange* Lists function key strings for the **-f** option.

See `rc.conf(5)` for details.

### Driver Configuration

The keyboard device driver may let you change default configuration options, such as the default keyboard map, so that you do not need to set up the options at boot time. See keyboard driver manuals (e.g. `atkbd(4)`, `ukbd(4)`) for details.

## FILES

`/usr/share/syscons/keymaps/*` keyboard map files for `syscons`  
`/usr/share/vt/keymaps/*` keyboard map files for `vt`

## EXAMPLES

The following command will load the keyboard map file `/usr/share/syscons/keymaps/ru.koi8-r.kbd`.

```
kbdcontrol -l /usr/share/syscons/keymaps/ru.koi8-r.kbd
```

So long as the keyboard map file resides in `/usr/share/syscons/keymaps` (if using `syscons(4)`) or `/usr/share/vt/keymaps` (if using `vt(4)`), you may abbreviate the file name as `ru.koi8-r`. Since `vt(4)` uses Unicode, the corresponding keyboard file names omit the encoding and typically are just a country code, e.g. `ru`.

```
kbdcontrol -l ru.koi8-r
```

The following command will make the function key 10 emit "telnet myhost".

```
kbdcontrol -f 10 "telnet myhost"
```

In order to get the visual effect for bell, but prevent the screen from flashing if the bell is to ring in the background screen, run the following command.

```
kbdcontrol -b quiet.visual
```

To change the default console keyboard to another keyboard, for example the first USB keyboard (see `ukbd(4)`), use the following command.

```
kbdcontrol -k /dev/ukbd0 < /dev/console
```

To switch back to the default keyboard, use this command.

```
kbdcontrol -k /dev/kbd0
```

To allow using both the second USB keyboard and the first AT keyboard at the same time on console via the `kbdmux(4)` driver, use the following sequence of commands.

```
kbdcontrol -K < /dev/console  
kbdcontrol -a atkbd0 < /dev/kbdmux0  
kbdcontrol -a ukbd1 < /dev/kbdmux0  
kbdcontrol -k /dev/kbdmux0 < /dev/console
```

## SEE ALSO

`kbdmap(1)`, `vidcontrol(1)`, `atkbd(4)`, `kbdmux(4)`, `keyboard(4)`, `screen(4)`, `syscons(4)`, `ukbd(4)`, `vt(4)`, `kbdmap(5)`, `rc.conf(5)`

## AUTHORS

Søren Schmidt <[sos@FreeBSD.org](mailto:sos@FreeBSD.org)>

## BUGS

Report when found.