NAME

uconv - convert data from one encoding to another

SYNOPSIS

DESCRIPTION

uconv converts, or transcodes, each given *file* (or its standard input if no *file* is specified) from one *encoding* to another. The transcoding is done using Unicode as a pivot encoding (i.e. the data are first transcoded from their original encoding to Unicode, and then from Unicode to the destination encoding).

If an *encoding* is not specified or is -, the default encoding is used. Thus, calling **uconv** with no *encoding* provides an easy way to validate and sanitize data files for further consumption by tools requiring data in the default encoding.

When calling **uconv**, it is possible to specify callbacks that are used to handle invalid characters in the input, or characters that cannot be transcoded to the destination encoding. Some encodings, for example, offer a default substitution character that can be used to represent the occurrence of such characters in the input. Other callbacks offer a useful visual representation of the invalid data.

uconv can also run the specified *transliteration* on the transcoded data, in which case transliteration will happen as an intermediate step, after the data have been transcoded to Unicode. The *transliteration* can be either a list of semicolon-separated transliterator names, or an arbitrarily complex set of rules in the ICU transliteration rules format.

For transcoding purposes, **uconv** options are compatible with those of **iconv**(1), making it easy to replace it in scripts. It is not necessarily the case, however, that the encoding names used by **uconv** and ICU are the same as the ones used by **iconv**(1). Also, options that provide informational data, such as the **-l**, **--list** one offered by some **iconv**(1) variants such as GNU's, produce data in a slightly different and easier to parse format.

OPTIONS

```
-h, -?, --help
```

Print help about usage and exit.

-V, --version

Print the version of **uconv** and exit.

-s, --silent

Suppress messages during execution.

-v, --verbose

Display extra informative messages during execution.

-l, --list

List all the available encodings and exit.

-l, --list-code code

List only the *code* encoding and exit. If *code* is not a proper encoding, exit with an error.

--default-code

List only the name of the default encoding and exit.

-L, --list-transliterators

List all the available transliterators and exit.

--canon

If used with -l, --list or --default-code, the list of encodings is produced in a format compatible with **convrtrs.txt**(5). If used with -L, --list-transliterators, print only one transliterator name per line.

-x transliteration

Run the given *transliteration* on the transcoded Unicode data, and use the transliterated data as input for the transcoding to the destination encoding.

--to-callback callback

Use *callback* to handle characters that cannot be transcoded to the destination encoding. See section **CALLBACKS** for details on valid callbacks.

-c Omit invalid characters from the output. Same as --to-callback skip.

--from-callback callback

Use *callback* to handle characters that cannot be transcoded from the original encoding. See section **CALLBACKS** for details on valid callbacks.

-i Ignore invalid sequences in the input. Same as --from-callback skip.

--callback callback

Use *callback* to handle both characters that cannot be transcoded from the original encoding and characters that cannot be transcoded to the destination encoding. See section **CALLBACKS** for details on valid callbacks.

--fallback

Use the fallback mapping when transcoding from Unicode to the destination encoding.

--no-fallback

Do not use the fallback mapping when transcoding from Unicode to the destination encoding. This is the default.

-b, --block-size size

Read input in blocks of *size* bytes at a time. The default block size is 4096.

-f, --from-code encoding

Set the original encoding of the data to encoding.

-t, --to-code encoding

Transcode the data to encoding.

--add-signature

Add a U+FEFF Unicode signature character (BOM) if the output charset supports it and does not add one anyway.

--remove-signature

Remove a U+FEFF Unicode signature character (BOM).

-o, --output file

Write the transcoded data to file.

CALLBACKS

uconv supports specifying callbacks to handle invalid data. Callbacks can be set for both directions of transcoding: from the original encoding to Unicode, with the **--from-callback** option, and from Unicode to the destination encoding, with the **--to-callback** option.

The following is a list of valid *callback* names, along with a description of their behavior. The list of callbacks actually supported by **uconv** is displayed when it is called with **-h**, **--help**.

substitute Write the encoding's substitute sequence, or the Unicode replacement character

U+FFFD when transcoding to Unicode.

skip Ignore the invalid data.

stop Stop with an error when encountering invalid data. This is the default callback.

escape Same as **escape-icu**.

escape-icu Replace the missing characters with a string of the format %Uhhhh for plane 0

characters, and %Uhhhh%Uhhhh for planes 1 and above characters, where hhhh is the hexadecimal value of one of the UTF-16 code units representing the character. Characters from planes 1 and above are written as a pair of UTF-16

surrogate code units.

escape-java Replace the missing characters with a string of the format \uhbhhh for plane 0

characters, and \uhhhh\uhhhh for planes 1 and above characters, where hhhh is the hexadecimal value of one of the UTF-16 code units representing the

character. Characters from planes 1 and above are written as a pair of UTF-16

surrogate code units.

escape-c Replace the missing characters with a string of the format \u21b1hhh for plane 0

characters, and \Uhhhhhhhh for planes 1 and above characters, where hhhh and

hhhhhhhh are the hexadecimal values of the Unicode codepoint.

escape-xml Same as escape-xml-hex.

escape-xml-hex Replace the missing characters with a string of the format &#xhhhh;, where

hhhh is the hexadecimal value of the Unicode codepoint.

escape-xml-dec Replace the missing characters with a string of the format &#nnnn; where nnnn

is the decimal value of the Unicode codepoint.

escape-unicode Replace the missing characters with a string of the format {U+hhhh}, where

hhhh is the hexadecimal value of the Unicode codepoint. That hexadecimal string is of variable length and can use from 4 to 6 digits. This is the format universally used to denote a Unicode codepoint in the literature, delimited by

curly braces for easy recognition of those substitutions in the output.

EXAMPLES

Convert data from a given *encoding* to the platform encoding:

```
$ uconv -f encoding
```

Check if a *file* contains valid data for a given *encoding*:

```
$ uconv -f encoding -c file >/dev/null
```

Convert a UTF-8 *file* to a given *encoding* and ensure that the resulting text is good for any version of HTML:

```
$ uconv -f utf-8 -t encoding \
--callback escape-xml-dec file
```

Display the names of the Unicode code points in a UTF-file:

```
$ uconv -f utf-8 -x any-name file
```

Print the name of a Unicode code point whose value is known (U+30AB in this example):

```
$ echo '\u30ab' | uconv -x 'hex-any; any-name'; echo
{KATAKANA LETTER KA}{LINE FEED}
$
```

(The names are delimited by curly braces. Also, the name of the line terminator is also displayed.)

Normalize UTF-8 data using Unicode NFKC, remove all control characters, and map Katakana to Hiragana:

```
$ uconv -f utf-8 -t utf-8 \
-x '::nfkc; [:Cc:] >; ::katakana-hiragana;'
```

CAVEATS AND BUGS

uconv does report errors as occurring at the first invalid byte encountered. This may be confusing to users of GNU **iconv**(1), which reports errors as occurring at the first byte of an invalid sequence. For multi-byte character sets or encodings, this means that **uconv** error positions may be at a later offset in the input stream than would be the case with GNU **iconv**(1).

The reporting of error positions when a transliterator is used may be inaccurate or unavailable, in which case **uconv** will report the offset in the output stream at which the error occurred.

AUTHORS

Jonas Utterstroem Yves Arrouye

VERSION

73.2

COPYRIGHT

Copyright (C) 2000-2005 IBM, Inc. and others.

SEE ALSO

iconv(1)