#### **NAME**

wLog - WinPR logging facility

#### DESCRIPTION

wLog is a configurable and flexible logging system used throughout WinPR and FreeRDP.

The primary concept is to have a hierarchy of loggers that can be be configured independently.

# **Appenders**

WLog uses different appenders that define where the log output should be written to. If the application doesn't explicitly configure the appenders the below described variable WLOG\_APPENDER can be used to choose one appender.

The following kind of appenders are available:

# **Binary**

Write the log data into a binary format file.

#### Console

The console appender writes to the console. Depending of the operating system the application runs on, the output might be handled differently. For example on android log print would be used.

File

The file appender writes the textual output to a file.

Udp

This appender sends the logging messages to a pre-defined remote host via UDP.

If no target is set the default one 127.0.0.1:20000 is used. To receive the log messages one can use netcat. To receive the default target the following command can be used: nc -u 127.0.0.1 -p 20000 -1

# Syslog

Use syslog for outputting the debug messages.

Journald

This appender outputs messages to journald.

#### Levels

The WLog are complementary, the higher level always includes the lower ones. The level list below is top down. Top the highest level.

# **TRACE**

print everything including packets dumps

### **DEBUG**

debug messages

### **INFO**

general information

## WARN

warnings

### **ERROR**

errors

## **FATAL**

fatal problems

### **OFF**

completely disable the wlog output

#### **Formats**

The format a logger prints has the following possible options:

lv log level

mn module name

fl file name

fn function

In line number

pid process id

tid thread id

yr year

mo month

dw day of week

hr hour

mi minute

se second

ml millisecond

A maximum of 16 options can be used per format string.

An example that generally sets the WLOG\_PREFIX for xfreerdp would look like: WLOG\_PREFIX="pid=%pid:tid=%tid:fn=%fn -" xfreerdp /v:xxx

## **ENVIRONMENT**

WLOG\_APPENDER

The kind of appender, the accepted values are: CONSOLE, FILE, BINARY, SYSLOG, JOURNALD or UDP

WLOG\_PREFIX

configure the prefix used for outputting the message (see Format for more details and examples)

WLOG\_LEVEL

the level to output messages for

# WLOG\_FILTER

sets a filter for WLog messages. Only the filtered messages are printed. The format of the filter is a series of <logger name>:<level> separated by comas

example: WLOG\_FILTER=core.channel:DEBUG,dummy:TRACE will display debug messages for the core.channel logger and trace level for the dummy logger

## WLOG\_FILEAPPENDER\_OUTPUT\_FILE\_PATH

When using the file appender it may contains the output log file's path

### WLOG\_FILEAPPENDER\_OUTPUT\_FILE\_NAME

When using the file appender it may contains the output log file's name

# WLOG\_JOURNALD\_ID

When using the systemd journal appender, this variable contains the id used with the journal (by default the executable's name)

### WLOG\_UDP\_TARGET

target to use for the UDP appender in the format host:port

#### **BUGS**

Please report any bugs using the bug reporting form on the FreeRDP web site

#### **SEE ALSO**

Additional information and the latest version is available at the web site: http://www.freerdp.com

# **AUTHOR**

David Fort <contact@hardening-consulting.com> wrote this manpage from materials written by Bernhard Miklautz <br/> <br/> dernhard.miklautz@thincast.com>.