

NAME

SSL_SESSION_get0_hostname, SSL_SESSION_set1_hostname, SSL_SESSION_get0_alpn_selected, SSL_SESSION_set1_alpn_selected - get and set SNI and ALPN data associated with a session

SYNOPSIS

```
#include <openssl/ssl.h>
```

```
const char *SSL_SESSION_get0_hostname(const SSL_SESSION *s);
int SSL_SESSION_set1_hostname(SSL_SESSION *s, const char *hostname);
```

```
void SSL_SESSION_get0_alpn_selected(const SSL_SESSION *s,
                                   const unsigned char **alpn,
                                   size_t *len);
```

```
int SSL_SESSION_set1_alpn_selected(SSL_SESSION *s, const unsigned char *alpn,
                                   size_t len);
```

DESCRIPTION

SSL_SESSION_get0_hostname() retrieves the SNI value that was sent by the client when the session was created if it was accepted by the server and TLSv1.2 or below was negotiated. Otherwise NULL is returned. Note that in TLSv1.3 the SNI hostname is negotiated with each handshake including resumption handshakes and is therefore never associated with the session.

The value returned is a pointer to memory maintained within **s** and should not be free'd.

SSL_SESSION_set1_hostname() sets the SNI value for the hostname to a copy of the string provided in **hostname**.

SSL_SESSION_get0_alpn_selected() retrieves the selected ALPN protocol for this session and its associated length in bytes. The returned value of ***alpn** is a pointer to memory maintained within **s** and should not be free'd.

SSL_SESSION_set1_alpn_selected() sets the ALPN protocol for this session to the value in **alpn** which should be of length **len** bytes. A copy of the input value is made, and the caller retains ownership of the memory pointed to by **alpn**.

RETURN VALUES

SSL_SESSION_get0_hostname() returns either a string or NULL based on if there is the SNI value sent by client.

SSL_SESSION_set1_hostname() returns 1 on success or 0 on error.

SSL_SESSION_GET0_HOSTNAME(3openssl) OpenSSL SSL_SESSION_GET0_HOSTNAME(3openssl)

SSL_SESSION_set1_alpn_selected() returns 1 on success or 0 on error.

SEE ALSO

`ssl(7)`, `d2i_SSL_SESSION(3)`, `SSL_SESSION_get_time(3)`, `SSL_SESSION_free(3)`

HISTORY

The `SSL_SESSION_set1_hostname()`, `SSL_SESSION_get0_alpn_selected()` and `SSL_SESSION_set1_alpn_selected()` functions were added in OpenSSL 1.1.1.

COPYRIGHT

Copyright 2016-2020 The OpenSSL Project Authors. All Rights Reserved.

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at <https://www.openssl.org/source/license.html>.