#### **NAME**

pcap\_findalldevs, pcap\_freealldevs - get a list of capture devices, and free that list

## **SYNOPSIS**

```
#include <pcap/pcap.h>
char errbuf[PCAP_ERRBUF_SIZE];
int pcap_findalldevs(pcap_if_t **alldevsp, char *errbuf);
void pcap_freealldevs(pcap_if_t *alldevs);
```

#### DESCRIPTION

pcap\_findalldevs() constructs a list of network devices that can be opened with pcap\_create(3) and pcap\_activate(3) or with pcap\_open\_live(3). (Note that there may be network devices that cannot be opened by the process calling pcap\_findalldevs(), because, for example, that process does not have sufficient privileges to open them for capturing; if so, those devices will not appear on the list.) If pcap\_findalldevs() succeeds, the pointer pointed to by *alldevsp* is set to point to the first element of the list, or to NULL if no devices were found (this is considered success). Each element of the list is of type pcap\_if\_t, and has the following members:

#### next

if not NULL, a pointer to the next element in the list; NULL for the last element of the list

## name

a pointer to a string giving a name for the device to pass to pcap\_open\_live()

## description

if not NULL, a pointer to a string giving a human-readable description of the device

## addresses

a pointer to the first element of a list of network addresses for the device, or **NULL** if the device has no addresses

## flags

device flags:

# PCAP\_IF\_LOOPBACK

set if the device is a loopback interface

PCAP\_IF\_UP

set if the device is up

## PCAP\_IF\_RUNNING

set if the device is running

## PCAP IF WIRELESS

set if the device is a wireless interface; this includes IrDA as well as radio-based networks such as IEEE 802.15.4 and IEEE 802.11, so it doesn't just mean Wi-Fi

# PCAP\_IF\_CONNECTION\_STATUS

a bitmask for an indication of whether the adapter is connected or not; for wireless interfaces, "connected" means "associated with a network"

The possible values for the connection status bits are:

## PCAP\_IF\_CONNECTION\_STATUS\_UNKNOWN

it's unknown whether the adapter is connected or not

# PCAP\_IF\_CONNECTION\_STATUS\_CONNECTED

the adapter is connected

## PCAP\_IF\_CONNECTION\_STATUS\_DISCONNECTED

the adapter is disconnected

# PCAP\_IF\_CONNECTION\_STATUS\_NOT\_APPLICABLE

the notion of "connected" and "disconnected" don't apply to this interface; for example, it doesn't apply to a loopback device

Each element of the list of addresses is of type **pcap\_addr\_t**, and has the following members:

## next

if not NULL, a pointer to the next element in the list; NULL for the last element of the list

## addr

a pointer to a struct sockaddr containing an address

#### netmask

if not **NULL**, a pointer to a **struct sockaddr** that contains the netmask corresponding to the address pointed to by **addr** 

#### broadaddr

if not **NULL**, a pointer to a **struct sockaddr** that contains the broadcast address corresponding to the address pointed to by **addr**; may be null if the device doesn't support broadcasts

#### dstaddr

if not **NULL**, a pointer to a **struct sockaddr** that contains the destination address corresponding to the address pointed to by **addr**; may be null if the device isn't a point-to-point interface

Note that the addresses in the list of addresses might be IPv4 addresses, IPv6 addresses, or some other type of addresses, so you must check the **sa\_family** member of the **struct sockaddr** before interpreting the contents of the address; do not assume that the addresses are all IPv4 addresses, or even all IPv4 or IPv6 addresses. IPv4 addresses have the value **AF\_INET**, IPv6 addresses have the value **AF\_INET6** (which older operating systems that don't support IPv6 might not define), and other addresses have other values. Whether other addresses are returned, and what types they might have is platform-dependent. For IPv4 addresses, the **struct sockaddr** pointer can be interpreted as if it pointed to a **struct sockaddr\_in**; for IPv6 addresses, it can be interpreted as if it pointed to a **struct sockaddr\_in**.

The list of devices must be freed with **pcap\_freealldevs**(3), which frees the list pointed to by *alldevs*.

## RETURN VALUE

**pcap\_findalldevs**() returns **0** on success and **PCAP\_ERROR** on failure; as indicated, finding no devices is considered success, rather than failure, so **0** will be returned in that case. If **PCAP\_ERROR** is returned, *errbuf* is filled in with an appropriate error message. *errbuf* is assumed to be able to hold at least **PCAP\_ERRBUF\_SIZE** chars.

### BACKWARD COMPATIBILITY

The PCAP\_IF\_UP and PCAP\_IF\_RUNNING constants became available in libpcap release 1.6.1. The PCAP\_IF\_WIRELESS, PCAP\_IF\_CONNECTION\_STATUS,

PCAP\_IF\_CONNECTION\_STATUS\_UNKNOWN,

PCAP\_IF\_CONNECTION\_STATUS\_CONNECTED,

PCAP IF CONNECTION STATUS DISCONNECTED, and

**PCAP\_IF\_CONNECTION\_STATUS\_NOT\_APPLICABLE** constants became available in libpcap release 1.9.0.

## **SEE ALSO**

pcap(3)