library "libcap\_fileargs"

### **NAME**

fileargs\_cinit, fileargs\_cinitnv, fileargs\_init, fileargs\_initnv, fileargs\_free, fileargs\_lstat, fileargs\_open, fileargs\_fopen - library for handling files in capability mode

#### **LIBRARY**

```
#include <sys/nv.h>
#include #include #include <casper.h>
#include <casper/cap_fileargs.h>

fileargs_t *
fileargs_init(int argc, char *argv[], int flags, mode_t mode, cap_rights_t *rightsp, int operations);

fileargs_t *
fileargs_cinit(cap_channel_t *cas, int argc, char *argv[], int flags, mode_t mode, cap_rights_t *rightsp, int operations);

fileargs_t *
fileargs_cinitnv(cap_channel_t *cas, nvlist_t *limits);

fileargs_t *
fileargs_initnv(nvlist_t *limits);

void
fileargs_free(fileargs_t *fa);
```

```
\textbf{fileargs\_open}(fileargs\_t \ *fa, const \ char \ *name);
```

FILE \*

int

int

```
fileargs_fopen(fileargs_t *fa, const char *name, const char *mode);
```

**fileargs\_lstat**(*fileargs\_t* \**fa*, *const char* \**path*, *struct stat* \**sb*);

char \*

**fileargs\_realpath**(*fileargs\_t* \**fa*, *const char* \**pathname*, *char* \**reserved\_path*);

#### DESCRIPTION

The library is used to simplify Capsicumizing a tools that are using file system. Idea behind the library is that we are passing a remaining *argc* and *argv* which contains a list of files that should be open for this program. The library will create a service that will serve those files.

The function **fileargs\_init**() create a service to the **system.fileargs**. The *argv* contains a list of files that should be opened. The argument can be set to NULL which will not create a service and all files will be prohibited to be opened. The *argc* argument contains a number of passed files. The *flags* argument limits opened files for either execution or reading and/or writing. The *mode* argument tells which what mode file should be created if the O\_CREATE flag is present. For more details of the *flags* and *mode* arguments see open(2). The *rightsp* argument contains a list of the capability rights which file should be limited to. For more details of the capability rights see cap\_rights\_init(3). The *operations* argument limits the operations that are available using **system.fileargs**. *operations* is a combination of:

FA\_OPEN
Allow **fileargs\_open()** and **fileargs\_fopen()**.

FA\_LSTAT Allow **fileargs\_lstat**().

FA\_REALPATH Allow **fileargs\_realpath()**.

The function **fileargs\_cinit**() is equivalent to **fileargs\_init**() except that the connection to the Casper needs to be provided.

The functions **fileargs\_initnv**() and **fileargs\_cinitnv**() are respectively equivalent to **fileargs\_init**() and **fileargs\_cinit**() expect that all arguments all provided as nvlist(9). For details see *LIMITS*.

The *fileargs\_free* close connection to the **system.fileargs** service and free are structures. The function handle NULL argument.

The function **fileargs\_lstat**() is equivalent to lstat(2).

The functions **fileargs\_open**() and **fileargs\_fopen**() are respectively equivalent to open(2) and fopen(3) expect that all arguments are fetched from the *fileargs\_t* structure.

The function **fileargs\_realpath()** is equivalent to realpath(3).

#### LIMITS

This section describe which values and types should be used to pass arguments to the *system.fileargs* through the **fileargs\_initnv()** and **fileargs\_cinitnv()** functions. The nvlist(9) for that functions must contain the following values and types:

```
flags (NV_TYPE_NUMBER)
```

The *flags* limits opened files for either execution or reading and/or writing.

```
mode (NV TYPE NUMBER)
```

If in the *flags* argument the O\_CREATE flag was defined the nvlist(9) must contain the *mode*. The *mode* argument tells which what mode file should be created.

```
operations (NV_TYPE_NUMBER)
```

The *operations* limits the usable operations for *system.fileargs*. The possible values are explained as *operations* argument with **fileargs\_init**().

The nvlist(9) for that functions may contain the following values and types:

```
cap_rights (NV_TYPE_BINARY)
```

The *cap\_rights* argument contains a list of the capability rights which file should be limited to.

```
(NV TYPE NULL)
```

Any number of NV\_TYPE\_NULL where the name of the element is name of the file which can be opened.

#### **EXAMPLES**

The following example first parse some options and then create the **system.fileargs** service with remaining arguments.

```
argc -= optind;
   argv += optind;
  /* Create capability to the system.fileargs service. */
   fa = fileargs_init(argc, argv, O_RDONLY, 0,
     cap_rights_init(&rights, CAP_READ), FA_OPEN);
   if (fa == NULL)
             err(1, "unable to open system.fileargs service");
   /* Enter capability mode sandbox. */
   if (cap_enter() < 0 && errno != ENOSYS)
             err(1, "unable to enter capability mode");
   /* Open files. */
   for (i = 0; i < argc; i++) {
             fd = fileargs_open(fa, argv[i]);
             if (fd < 0)
                       err(1, "unable to open file %s", argv[i]);
             printf("File %s opened in capability mode\n", argv[i]);
             close(fd);
   }
  fileargs_free(fa);
SEE ALSO
   cap_enter(2), lstat(2), open(2), cap_rights_init(3), err(3), fopen(3), getopt(3), realpath(3), capsicum(4),
```

# HISTORY

nv(9)

The **cap\_fileargs** service first appeared in FreeBSD 10.3.

#### **AUTHORS**

Mariusz Zaborski <oshogbo@FreeBSD.org>

## **BUGS**

The library "cap\_fileargs" included in FreeBSD is considered experimental, and should not be deployed in production environments without careful consideration of the risks associated with the use of experimental operating system features.