

NAME

kvm_dpcpu_setcpu, **kvm_getmaxcpu**, **kvm_getpcpu** - access per-CPU data

LIBRARY

Kernel Data Access Library (libkvm, -lkvm)

SYNOPSIS

```
#include <sys/param.h>
```

```
#include <sys/pcpu.h>
```

```
#include <sys/sysctl.h>
```

```
#include <kvm.h>
```

int

```
kvm_dpcpu_setcpu(kvm_t *kd, u_int cpu);
```

int

```
kvm_getmaxcpu(kvm_t *kd);
```

int

```
kvm_getncpus(kvm_t *kd);
```

void *

```
kvm_getpcpu(kvm_t *kd, int cpu);
```

ssize_t

```
kvm_read_zpcpu(kvm_t *kd, u_long base, void *buf, size_t size, int cpu);
```

uint64_t

```
kvm_counter_u64_fetch(kvm_t *kd, u_long base);
```

DESCRIPTION

The **kvm_dpcpu_setcpu**(), **kvm_getmaxcpu**(), and **kvm_getpcpu**() functions are used to access the per-CPU data of active processors in the kernel indicated by *kd*. Per-CPU storage comes in two flavours: data stored directly in a *struct pcpu* associated with each CPU, and dynamic per-CPU storage (DPCPU), in which a single kernel symbol refers to different data depending on what CPU it is accessed from.

The **kvm_getmaxcpu**() function returns the maximum number of CPUs supported by the kernel.

The **kvm_getncpus**() function returns the current number of CPUs in the kernel.

The **kvm_getpcpu()** function returns a buffer holding the per-CPU data for a single CPU. This buffer is described by the *struct pcpu* type. The caller is responsible for releasing the buffer via a call to **free(3)** when it is no longer needed. If *cpu* is not active, then NULL is returned instead.

The **kvm_read_zpcpu()** function is used to obtain private per-CPU copy from a **UMA_ZONE_PCPU** zone(9). It takes *base* argument as base address of an allocation and copies *size* bytes into *buf* from the part of allocation that is private to *cpu*.

The **kvm_counter_u64_fetch()** function fetches value of a counter(9) pointed by *base* address.

Symbols for dynamic per-CPU data are accessed via **kvm_nlist(3)** as with other symbols. **libkvm** maintains a notion of the "current CPU", set by **kvm_dpcpu_setcpu()**, which defaults to 0. Once another CPU is selected, **kvm_nlist(3)** will return pointers to that data on the appropriate CPU.

CACHING

kvm_getmaxcpu() and **kvm_getpcpu()** cache the **nlist** values for various kernel variables which are reused in successive calls. You may call either function with *kd* set to NULL to clear this cache.

RETURN VALUES

On success, the **kvm_getmaxcpu()** function returns the maximum number of CPUs supported by the kernel. If an error occurs, it returns -1 instead.

On success, the **kvm_getpcpu()** function returns a pointer to an allocated buffer or NULL. If an error occurs, it returns -1 instead.

On success, the **kvm_dpcpu_setcpu()** call returns 0; if an error occurs, it returns -1 instead.

On success, the **kvm_read_zpcpu()** function returns number of bytes copied. If an error occurs, it returns -1 instead.

If any function encounters an error, then an error message may be retrieved via **kvm_geterr(3)**.

SEE ALSO

free(3), **kvm(3)**, **counter(9)**, **zone(9)**