

NAME

pxeboot - Preboot Execution Environment (PXE) bootloader

DESCRIPTION

The **pxeboot** bootloader is a modified version of the system third-stage bootstrap loader(8) configured to run under Intel's Preboot Execution Environment (PXE) system. PXE is a form of smart boot ROM, built into Intel EtherExpress Pro/100 and 3Com 3c905c Ethernet cards, and Ethernet-equipped Intel motherboards. PXE supports DHCP configuration and provides low-level NIC access services.

The DHCP client will set a DHCP user class named *FreeBSD* to allow flexible configuration of the DHCP server.

The **pxeboot** bootloader retrieves the kernel, modules, and other files either via NFS over UDP or by TFTP, selectable through compile-time options. In combination with a memory file system image or NFS-mounted root file system, **pxeboot** allows for easy, EEPROM-burner free construction of diskless machines.

The **pxeboot** binary is loaded just like any other boot file, by specifying it in the DHCP server's configuration file. Below is a sample configuration for the ISC DHCP v3 server:

```
option domain-name "example.com";
option routers 10.0.0.1;
option subnet-mask 255.255.255.0;
option broadcast-address 10.0.0.255;
option domain-name-servers 10.0.0.1;
server-name "DHCPserver";
server-identifier 10.0.0.1;
next-server 10.0.0.1;

default-lease-time 120;
max-lease-time 120;

subnet 10.0.0.0 netmask 255.255.255.0 {
    filename "pxeboot";
    range 10.0.0.10 10.0.0.254;
    if exists user-class and option user-class = "FreeBSD" {
        option root-path "tftp://10.0.0.1/FreeBSD";
    }
}
```

next-server is the IP address of the next server in the bootstrap process, i.e. your TFTP server or NFS server. **pxeboot** recognizes *option root-path* directives as the server and path to NFS mount for file requests, respectively, or the server to make TFTP requests to. Note that **pxeboot** expects to fetch */boot/loader.rc* from the specified server before loading any other files.

Valid *option root-path* syntax is the following

<i>/path</i>	path to the root filesystem on the NFS server
<i>ip://path</i>	path to the root filesystem on the NFS server <i>ip</i>
<i>nfs://path</i>	path to the root filesystem on the NFS server
<i>nfs://ip/path</i>	path to the root filesystem on the NFS server <i>ip</i>
<i>tftp://path</i>	path to the root filesystem on the TFTP server
<i>tftp://ip/path</i>	path to the root filesystem on the TFTP server <i>ip</i>

pxeboot defaults to a conservative 1024 byte NFS data packet size. This may be changed by setting the *nfs.read_size* variable in */boot/loader.conf*. Valid values range from 1024 to 16384 bytes.

In all other respects, **pxeboot** acts just like `loader(8)`.

For further information on Intel's PXE specifications and Wired for Management (WfM) systems, see <http://www.pix.net/software/pxeboot/archive/pxespec.pdf>.

SEE ALSO

`loader(8)`

HISTORY

The **pxeboot** bootloader first appeared in FreeBSD 4.1.

AUTHORS

The **pxeboot** bootloader was written by John Baldwin <jhb@FreeBSD.org> and Paul Saab <ps@FreeBSD.org>. This manual page was written by Doug White <dwhite@FreeBSD.org>.