

**NAME**

**zfs-mount** - manage mount state of ZFS filesystems

**SYNOPSIS**

**zfs mount**

**zfs mount** [-Oflv] [-o *options*] -a|*filesystem*

**zfs unmount** [-fu] -a|*filesystem*|*mountpoint*

**DESCRIPTION**

**zfs mount**

Displays all ZFS file systems currently mounted.

**zfs mount** [-Oflv] [-o *options*] -a|*filesystem*

Mount ZFS filesystem on a path described by its **mountpoint** property, if the path exists and is empty. If **mountpoint** is set to *legacy*, the filesystem should be instead mounted using mount(8).

**-O** Perform an overlay mount. Allows mounting in non-empty **mountpoint**. See mount(8) for more information.

**-a** Mount all available ZFS file systems. Invoked automatically as part of the boot process if configured.

*filesystem*

Mount the specified filesystem.

**-o options**

An optional, comma-separated list of mount options to use temporarily for the duration of the mount. See the *Temporary Mount Point Properties* section of zfsprops(7) for details.

**-l** Load keys for encrypted filesystems as they are being mounted. This is equivalent to executing **zfs load-key** on each encryption root before mounting it. Note that if a filesystem has **keylocation=prompt**, this will cause the terminal to interactively block after asking for the key.

**-v** Report mount progress.

**-f** Attempt to force mounting of all filesystems, even those that couldn't normally be mounted (e.g. redacted datasets).

**zfs unmount** [-fu] -a|*filesystem*|*mountpoint*

Unmounts currently mounted ZFS file systems.

- a** Unmount all available ZFS file systems. Invoked automatically as part of the shutdown process.
- f** Forcefully unmount the file system, even if it is currently in use. This option is not supported on Linux.
- u**  
Unload keys for any encryption roots unmounted by this command.

*filesystem|mountpoint*

Unmount the specified filesystem. The command can also be given a path to a ZFS file system mount point on the system.