#### **NAME**

mate-session-save - End or save the current MATE session

#### **SYNOPSIS**

mate-session-save [--logout] [--force-logout] [--logout-dialog] [--shutdown-dialog] [--gui] [--kill [--silent]]

# DESCRIPTION

The **mate-session-save** program can be used from a MATE session to either end the current MATE session or save a snapshot of the currently running applications (but not both). This session will be later restored at your next MATE session.

#### **USAGE**

The **--gui** option will report errors in dialog boxes instead of printing to stderr.

If called with the **--logout** option, the current MATE session will be ended, unless logging out has been inhibited by an application. The **--force-logout** option can be used to end the session regardless of the inhibition state.

When the **--logout-dialog** option is given, the standard dialog displaying logout options is displayed. When **--shutdown-dialog** option is given, the standard dialog displaying shutdown options is displayed.

The --kill and --silent options are deprecated. The --kill option is equivalent to the --logout-dialog option. If --silent is used with --kill, then it will behave as if --logout was used.

The session is not saved when **mate-session-save** is called with any of the options ending the session.

## **OPTIONS**

## --logout

Log out

### --force-logout

Log out, ignoring any existing inhibitors

## --logout-dialog

Show logout dialog

### --shutdown-dialog

Show shutdown dialog

## --gui

Use dialog boxes for errors

# --display=DISPLAY

X display to use.

#### --version

Output version information and exit.

## -?, -h, --help

Print standard command line options.

# --help-all

Print all command line options.

## **BUGS**

## Should you encounter any bugs, they may be reported at:

http://github.com/mate-desktop/mate-session-manager/issues

## **AUTHORS**

## This Man Page has been updated/re-written for the MATE Desktop Environment by:

Adam Erdman < hekel@archlinux.info> (2014)

## **HISTORY**

## This Manual was originally written for gnome-session by:

Miguel de Icaza <miguel@helixcode.com> (2000)

Vincent Untz <vuntz@gnome.org> (2009-2010)

## **SEE ALSO**

Further information may also be available at: http://wiki.mate-desktop.org/docs mate-session-properties(1), mate-wm(1), mate-session(1)