

NAME

mknod - build special file

SYNOPSIS

mknod *name*

mknod *name* [**b** | **c**] *major minor* [*owner:group*]

DESCRIPTION

The *mknod* utility is deprecated on modern FreeBSD systems.

The **mknod** utility creates device special files. To make nodes manually, the arguments are:

name Device name, for example */dev/da0* for a SCSI disk or */dev/pts/0* for pseudo-terminals.

b | **c** Type of device. If the device is a block type device such as a tape or disk drive which needs both cooked and raw special files, the type is **b**. All other devices are character type devices, such as terminal and pseudo devices, and are type **c**.

major The major device number is an integer number which tells the kernel which device driver entry point to use.

minor The minor device number tells the kernel which subunit the node corresponds to on the device; for example, a subunit may be a file system partition or a tty line.

owner:group

The *owner group* operand pair is optional, however, if one is specified, they both must be specified. The *owner* may be either a numeric user ID or a user name. If a user name is also a numeric user ID, the operand is used as a user name. The *group* may be either a numeric group ID or a group name. Similar to the user name, if a group name is also a numeric group ID, the operand is used as a group name.

Major and minor device numbers can be given in any format acceptable to `strtoul(3)`, so that a leading '0x' indicates a hexadecimal number, and a leading '0' will cause the number to be interpreted as octal.

The **mknod** utility can be used to recreate deleted device nodes under a `devfs(5)` mount point by invoking it with only a filename as an argument. Example:

```
mknod /dev/cd0
```

where */dev/cd0* is the name of the deleted device node.

COMPATIBILITY

The `chown(8)`-like functionality is specific to FreeBSD.

As of FreeBSD 4.0, block devices were deprecated in favour of character devices. As of FreeBSD 5.0, device nodes are managed by the device file system `devfs(5)`, making the **`mknod`** utility superfluous. As of FreeBSD 6.0 device nodes may be created in regular file systems but such nodes cannot be used to access devices.

SEE ALSO

`mkfifo(1)`, `mknod(2)`, `devfs(5)`, `chown(8)`

HISTORY

A **`mknod`** utility appeared in Version 4 AT&T UNIX.