

NAME

gslp - Format and print text using ghostscript
gsbj - Format and print text for BubbleJet printer using ghostscript
gsdj - Format and print text for DeskJet printer using ghostscript
gsdj500 - Format and print text for DeskJet 500 BubbleJet using ghostscript
gslj - Format and print text for LaserJet printer using ghostscript

SYNOPSIS

gslp **-12BclqRr** **-b**<header> **-f** **-F**<hfont> **-L**<lines> **-p**<outfile> **-T**<n> **--add-to-space** <units>
--add-to-width <units> **--columns** <n> **--detect** **--first-page** <n> **--kern** <file.afm> **--last-page** <n>
--(headingfooting)-(left|center|right) <string> **--margin-(top|bottom|left|right)** <inches>
--no-eject-(file|formfeed) **--spacing** <n> [**gs options**] [**files**]
gsbj [**options**] [**files**]
gsdj [**options**] [**files**]
gsdj500 [**options**] [**files**]
gslj [**options**] [**files**]

DESCRIPTION

This utility provides functionality approximately equivalent to the Unix **enscript**(1) program. It prints plain text files using a single font. It currently handles tabs and formfeeds, but not backspaces. It will line-wrap when using fixed-pitch fonts. It will also do kerning and width adjustment.

The default device (**-sDEVICE=**) and resolution (**-r**) are as follows:

```

gslp  epson    180
gsbj  bj10e   180
gsdj  deskjet 300
gsdj500 djet500 300
gslj  laserjet 300
  
```

By default the current date is formatted as the center header.

OPTIONS

Standard switches implemented:

-12BclqRr **-b**<header> **-f** **-F**<hfont> **-L**<lines> **-p**<outfile>

Sun switches implemented:

-T<n> set tab width

Switches ignored:

-GghKkmow **-#** **-C** **-d** **-J** **-n** **-P** **-S** **-s** **-t** **-v**

Switches added:

- `--add-to-space <units>`
add the given number of 1/72" units to the width of each space (may be negative)
- `--add-to-width <units>`
add the given number of 1/72" units to the width of each character (may be negative)
- `--columns <n>`
print in <n> columns
- `--detect`
treat the file as PostScript if it starts with %!
- `--first-page <n>`
start printing at page <n>
- `--kern <file.afm>`
kern using information from the given .AFM file
- `--last-page <n>`
stop printing after page <n>
- `--(heading|footing)-(left|center|right) <string>`
set the heading/footing fields; use `-B` first to clear
- `--margin-(top|bottom|left|right) <inches>`
set a margin
- `--no-eject-(file|formfeed)`
end-of-file/FF only starts a new column, not a new sheet
- `--spacing <n>`
use double (n=2), triple (n=3), etc. spacing

Also, the string `%#` in a heading or footing is replaced with the page #.

SEE ALSO

`gs(1)`

VERSION

This document was last revised for Ghostscript version 9.56.1.

AUTHOR

Artifex Software, Inc. are the primary maintainers of Ghostscript. This manpage by George Ferguson.